

ADDITIONAL SHEET

CCR# 04-0573

Rev: —

Originator: Iwuchukwu Junior.

Telephone: 301-925-0820

Office: 3000V

Title of Change: TE_7.02_PDS.01

CSG

Please make the following tar file from the REL7PTE containing the following packages:

IRIX65

/ecs/formal/STAGE/PDS/lib/irix65/pdsis.jar

Please label this tarfile: TE_7.02_PDS.01

This software delivery contains solutions for the following NCRs:

NCR	Subsystem	SEV	State	Site	Title
ECSed41359	OPS_PDS	1	R	GSFC	PDSIS Code not properly looking up granule sizes using PDSIS default

INSTALLATION:

The following provides the installation and configuration procedures to install TE_7.02_PDS.01

PATCH/TE DEPENDENCIES:

The mode must contain “ECS installed Custom Code “ at a minimum of 7.01 and Patch_7.01_PDS.02.

Note: These dependencies might be confusing but the PDS code prior to this delivery has not changed since 7.01 that is why we are still dependent on 7.01.

PRE-INSTALL:

01. Create a staging area for TE_7.02_PDS.01
02. Copy the tar file into the <staging_area>/IRIX65/ directory
03. Using the setup.ksh file untar the TE_7.02_PDS.01 tar file in the
 <staging_area>/IRIX65/directory
04. chmod 644 pdsis.jar
05. Logon to host where the .EcPdlsPDSIS.pkg is installed as pdsis[_mode] (xxdignn)
06. Shutdown the PDSIS server
 - a. ps -ef | grep java | grep pdsis[_mode] to get process id of the server.
 - b. Kill -9 <pid>

ADDITIONAL SHEET

CCR# 04-0573

Rev: —

Originator: Iwuchukwu Junior.

Telephone: 301-925-0820

Office: 3000V

Title of Change: TE_7.02_PDS.01

INSTALL:

01. Logon to host where the .EcPdlS PDSIS.pkg is installed as pdsis[_mode] (xxdignn)
02. cd /data1/pdsis[_mode]/lib/PDS/directory
03. cp <staging_area>/IRIX65/pdsis.jar .

POST-INSTALL:

01. Start PDSIS server
 - a. cd /data1/pdsis[_mode]/utilities.
 - b. EcPdPDSISServerStart pdsis[_mode]<true|false|super> &

Where true = debug information printed to debug log

false = no debug information printed to debug log

super = maximum debug information printed to debug log